



TechNote

TN040801-02

FunAsset Limited
Orchards
14 Townsend
Ilminster
Somerset
TA19 0AU
United Kingdom

Tel. + 44 (0)1460 57065
Fax + 44 (0)1460 53538

Email: support@funasset.com
Website: <http://www.funasset.com>

PKEYCHKDAY

Determine when the Passkey Expiry dialog starts to be displayed

Type: Configuration Parameter
Software Affected: SpoolQ run-time – SpoolQ.exe
Windows Tasks
Hardware Affected: None
FunAsset Contact: Mark Dowson / mark.dowson@funasset.com
Further Reference: Technical Reference Manual / SpoolQ User Guide

Introduction

A Configuration Parameter called **PKEYCHKDAY** has been added to the SpoolQ run-time (SpoolQ.exe) and all Windows Tasks.

NOTE: SpoolQ 2.0 D(M) contains the **PKEYCHKDAY** Configuration Parameter. For further details about other updates that have been included with this version, refer to TechNote TN040801-01.

Configuration Parameter

PKEYCHKDAY

Determines when the Passkey Expiry dialog starts to be displayed prior to expiration of the SpoolQ or Windows Task licence.

SET PKEYCHKDAY=VALUE

VALUES	DESCRIPTION	UNIT	DEFAULT
1 to 15	Day in the month prior to expiry of the licence.	dec	
NO	Two months prior to expiry of the licence for SpoolQ run-time. One month prior to expiry of the licence for Tasks.	n/a	• (SpoolQ run-time)
YES	One month prior to expiry of the licence.	n/a	• (Tasks)

NOTE: If the **PKEYCHKDAY** Configuration Parameter requires a value other than its default, it must be included within appropriate Task Configuration files and the SpoolQ Configuration file that is referenced within the Target box (command line) of the SpoolQ shortcut.

Availability

The latest SpoolQ run-time (SpoolQ.exe) and certain Windows Tasks can be downloaded from the following URL:

http://www.funasset.com/support/funasset_applications.htm

If you are unable to download the required files they can be requested as an email attachment or on CD by contacting FunAsset's Support Engineer, Gary Binding on + 44 (0)1460 57065 or by emailing gary.binding@funasset.com.